User's Guide

GoldSim Distributed Processing Module



GoldSim 15



Copyright GoldSim Technology Group LLC, 1998-2025. All rights reserved. GoldSim is a registered trademark of GoldSim Technology Group LLC.

GoldSim 15 (January 2025)

Document Revision: 0 (January 2, 2025)



GoldSim Technology Group LLC 255 S. King Street, Suite 800 Seattle, Washington 98104 USA

Visit us at <u>www.goldsim.com</u> Email us at <u>software@goldsim.com</u>

Contents

Chapter 1: Introduction

Chapter Overview	Į
In This Chapter 1	l
What is the Distributed Processing Module? 2)
Which Version (DP or DP Plus) Do I Have?)
Conventions Used in this Manual	3
The GoldSim Help System	3
Technical Support, User Resources and Software Upgrades	3
GoldSim Maintenance Program 4	ŀ
Getting Technical Support 4	ŀ
Other GoldSim Resources	ŀ

Chapter 2: Using the Distributed Processing Module

Chapter Overview	
In This Chapter	7
Overview of the Distributed Processing Module	8
Carrying out a Distributed Processing Simulation	8
Running GoldSim in Client Mode	
Connecting the Controller Process to the Clients	
Running a Distributed Processing Simulation	
Limitations of the Distributed Processing Module	
-	

Glossary

Index

27 29

1

7

Chapter 1: Introduction

Two heads are better than one.

Anonymous

Chapter Overview

GoldSim is a user-friendly, highly graphical, object-oriented program for carrying out dynamic, probabilistic simulations to support management and decision-making in engineering, science and business.

The GoldSim Distributed Processing Module is a program extension to GoldSim which allows you to use multiple computers connected over a network to share the computational burden of a Monte Carlo simulation.

Each of the GoldSim modules has a separate User's Guide describing its capabilities and features. This short document provides a complete description of the features and use of the GoldSim Distributed Processing Module.

Note: This document only describes the Distributed Processing Module, and assumes that you are familiar with the basic capabilities of GoldSim (described in the GoldSim User's Guide).

In This Chapter

This introductory chapter discusses the following topics:

- What is the Distributed Processing Module?
- Which Version (DP or DP Plus) Do I Have?
- Conventions Used in this Document
- Using Help
- Getting Technical Support

What is the Distributed Processing Module?

GoldSim was designed to provide a highly efficient simulation framework for use on a single Windows personal computer. For most applications, running your GoldSim application on a single machine will be sufficient. For highly complex models, however, running Monte Carlo simulations on a single machine could become impractical. For example, if each realization took one minute to complete, then 1000 realizations would take over 16 hours.

The Distributed Processing Module allows you to overcome this problem by combining the power of multiple cores and/or computers to carry out a simulation involving multiple realizations.

This is accomplished by a having a *Controller* GoldSim executable connect to an unlimited number of *Client* GoldSim executables. These Client processes can be on a single computer or on computers connected over a network. The Controller assigns and sends individual realizations to the Client processes. Each Client carries out its assigned realization, sends the results to the Controller, and then makes itself available to work on another realization. Once all of the realizations have been completed, the Controller process combines all of the results into a single GoldSim file (and enters Result Mode) just as if the entire simulation had been carried out on the Controller's machine.

Although the Controller and Client processes will typically be connected via a Local Area Network (LAN), they can also communicate via a Wide Area Network (WAN) or even the Internet. In general, the speed of the simulation is proportional to the number of available Client processes.

There are two versions of the Distributed Processing Module. **GoldSim DP** comes bundled with all versions of GoldSim, and limits the number of Client processes to four. **GoldSim DP** Plus allows an unlimited number of Client processes, and must be licensed separately.

Which Version (DP or DP Plus) Do I Have?

As pointed out above, there are two different versions of the Distributed Processing Module, and your copy of GoldSim will have one or the other. You can determine which version of the Distributed Processing Module is activated on your machine by selecting **Help**|**Licensing** from the main menu.

At the top of the dialog, the "Acquired License Features" section will list "DP Plus" if you have the DP Plus version. If you don't see "DP Plus", it means you have the standard version of the module that limits the number of Client processes to four.

GoldSim Licensing	×
Acquired License Features GoldSim + RT + RL + DP Plus	Details
Local License Management Activation ID: ✓ Fulfillment Details ✓ Product: GoldSim + DP + RL + RT (Enterprise) Latest Supported Version: 12.0 Licensee: GoldSim Technology Group LLC Expiration: 11/30/2017	Activate Return Borrow
Network License Configuration Address: Request:	Configure
Gold5im 12.0 (BETA) #331	Help Close

Conventions Used in this Manual

The following conventions are used in this manual:

Convention	Description
Important Terms	New and important terms are presented in bold italics. These terms all appear in the Glossary of Terms at the end of the document.
File Open	Menus and menu selections are separated by a vertical bar. For example, File Open means "Access the File menu and select Open".
Ctrl+C	Key combinations are shown using a "+" sign. For example, Ctrl+C means press the Control and C keys simultaneously.
Warning	This means watch out! Warnings typically alert you to potential pitfalls and problems that may occur if you perform (or fail to perform) a certain action.
Note	Notes highlight important information about a particular concept, topic or procedure, such as limitations on how a particular feature can be used, or alternative ways of carrying out an action.

In describing the various mouse actions, the following conventions are used:

Mouse Action	Definition
Click	Press and release the left mouse button once.
Double- click	Press and release the left mouse button twice in rapid succession.
Right-click	Press and release the right mouse button once.
Drag	Press the left mouse button, and while keeping it depressed, move the cursor to another location, then release the button.

The GoldSim Help System

GoldSim has an extensive in-product Help facility. The Help system can be accessed by selecting **Help** | **Help Topics** from the main GoldSim menu or the **Help** button (the question mark) on the standard toolbar. Pressing the **Help** button within any of the dialogs also provides access to Help (in a context-sensitive manner). All of the information in the User's Guides is accessible via GoldSim Help (with the exception of any Technical Appendices).

Technical Support, User Resources and Software Upgrades

The GoldSim Technology Group is dedicated to providing complete solutions for our customers. We pride ourselves in providing prompt and extensive support and resources to our users, and are committed to ensuring that

each installation of our software is successful and adds value to the customer.

GoldSim Maintenance Program

When you purchase GoldSim software, you receive one year of <u>Software Maintenance</u>, entitling you to the following:

- Free software upgrades so that you always have the latest version of the GoldSim software.
- Basic Technical Support via email (and if necessary, web meeting). Basic support covers installation and licensing questions, as well as questions about GoldSim's features and capabilities.

After the first year, if you wish to continue to have access to new versions and technical support, Software Maintenance can be extended each year with payment of an annual fee.

Note: Software maintenance is automatically included with GoldSim Leases.

Getting Technical Support

Users with active Software Maintenance can submit questions directly to the GoldSim support team. Evaluation users are also welcome to contact us with questions on GoldSim functionality. The <u>GoldSim Help Center</u> is the primary portal for technical support. You can submit your questions directly from the Help Center. If your register and log in through the Help Center, you will be able check the status and view a history of all of your support requests.

The Help Center also includes:

- The <u>GoldSim Forum</u>, where you can you can post questions to the GoldSim community, or just browse existing messages;
- Articles on licensing questions and modeling tips; and
- An archive of past webinars (which demonstrate GoldSim features and capabilities).

Free Basic Technical Support does <u>not</u> include consulting, model trouble-shooting or detailed assistance with applying GoldSim to a particular problem. Assistance of this nature is defined as <u>Advanced Technical Support</u>. Users may purchase Advanced Technical Support in pre-paid 10 hour blocks.

Other GoldSim Resources

In addition to the GoldSim Help Center, additional resources are also available. These three resources can be accessed directly from the GoldSim website (www.goldsim.com):

- Free <u>Online Training Courses</u> that provide you with a thorough understanding of the key concepts on which GoldSim is based and all of the fundamentals required to build complex models of nearly any kind of system.
- The <u>GoldSim Model Library</u>, which contains a collection of example models to allow you to see how specific features of GoldSim can be used and/or how GoldSim can be used for specific applications.
- The <u>GoldSim Blog</u>, which provides an informal mechanism for GoldSim staff to share their knowledge, point out some of the more advanced (and perhaps overlooked) GoldSim features, share and discuss common mistakes we see in GoldSim applications, discuss interesting applications, and keep you abreast of our plans for further GoldSim developments.

You can stay up to date on the latest GoldSim news by joining the <u>GoldSim LinkedIn Group</u>, which is primarily used for announcements (e.g., new versions, interesting applications).

Note: When you purchase GoldSim, you are entitled to a free one hour, live web-based training session in which one of our analysts provides an interactive training session via the Internet and telephone. You are strongly encouraged to take advantage of this free training.

Chapter 2: Using the Distributed Processing Module

R2-D2, you know better than to trust a strange computer.

C-3PO

Chapter Overview

This chapter provides the details about using the GoldSim Distributed Processing Module. After first providing an overview of how a distributed processing simulation is carried out, step-by-step procedures for carrying out such a simulation are described. The chapter closes with a discussion on the limitations of the Distributing Processing Module.

In This Chapter

This chapter discusses the following topics:

- Overview of the Distributed Processing Module
- Carrying Out a Distributed Processing Simulation
- Limitations of the Distributed Processing Module

Overview of the Distributed Processing Module

The Distributed Processing Module uses multiple copies of GoldSim (processes) running on multiple machines (and/or multiple processors or cores within a single machine) to share the computational burden of a Monte Carlo simulation.

A distributed processing simulation is controlled by a single *Controller process*. The Controller process is a version of GoldSim running on one machine which has the Distributed Processing Module enabled. Through a dialog accessed via a menu item, the Controller process can create connections with multiple *Client* GoldSim processes.

The Controller process assigns and sends individual realizations to the Client processes. Each Client process carries out its assigned realization, sends the results to the Controller process, and then makes itself available to work on another realization. Once all of the realizations have been completed, the Controller process combines all of the results into a single GoldSim file (and enters Result Mode) just as if the entire simulation had been carried out on the Controller process's machine.

The GoldSim model file (and other required files such as user-created DLLs or linked spreadsheets) need not be present on machines running Client processes. The Controller process automatically transfers any necessary files to the Client machines.

When running as a Client process, GoldSim is run in a special mode. Rather than launching GoldSim in the traditional manner on the machine running the Client, a GoldSim Client is launched from the command line (this can be done using a Windows shortcut or the Run option on the Windows Start menu). When running in Client mode, you cannot view or edit a GoldSim model. The only function that a Client serves is to receive, process, and send back realizations sent to it by a Controller process.

In order for the Controller process to access the Client processes, they must be local to the computer or accessible over a network.

Carrying out a Distributed Processing Simulation

The steps required to carry out a distributed processing simulation are as follows:

- 1. Launch one or more GoldSim processes on the machine(s) that you wish to utilize.
- 2. Open the GoldSim model file and connect the Controller process to the Client processes.
- 3. Run the simulation.

Each of these three steps is discussed in detail below.

Running GoldSim in Client Mode

In order to start a GoldSim Client process on a machine, GoldSim (or the GoldSim Player) must be installed. The GoldSim Player is automatically installed when GoldSim is installed, and is also available as a <u>free download</u>. To launch the GoldSim Player in Client mode, you must run the Player from the command line using the "-dpclient" parameter. Typically, this would be done by accessing the Windows Run option, which displays the following dialog:

📨 Run	×
	Type the name of a program, folder, document, or Internet resource, and Windows will open it for you.
Open:	m Files (x86)\GTG\GoldSim 14.0\GSPlayer.exe" -dpclient 🗸
	OK Cancel Browse

You must enter the full path to the GoldSim Player executable (which may, of course, be different from that shown above), followed by the "-dpclient" command line parameter.

Note: In addition to using the GoldSim Player as a Client, any GoldSim executable (even if it is unregistered) can also be accessed as a Client. In this case, of course, the command line to run the Client would reference the GoldSim executable (GoldSim.exe) rather than the Player executable.

You could accomplish the same thing by creating and running a shortcut to the GoldSim Player executable with the appropriate command line parameter:

Security	Details	Previous Versions
General	Shortcut	Compatibility
GS	Player.exe - Shortcut	
arget location:	GoldSim 14.0	
arget:	x86)\GTG\GoldSim 14	.0\GSPlayer.exe" -dpclient
itart in: Shortcut kev:	"C:\Program Files (x86)\GTG\GoldSim 14.0"
Run:	Minimized	~
Comment:		
Open File La	cation Change Ic	on Advanced

In this particular case, the GoldSim Player would be launched in Client mode and immediately minimized.

If you placed this shortcut in the StartUp directory of the machine, the GoldSim Player would be loaded in Client mode whenever the machine was booted.

Note: When creating the shortcut, the pathname to the Player file must be enclosed in quotes, with the – dpclient option (to start the Player in Client mode) following the pathname. For example, if the path to the GoldSim Player was C:\Program Files (x86)\GTG\GoldSim 14.0\GSPlayer.exe, the Target field of the shortcut dialog should be "C:\Program Files (x86)\GTG\GoldSim 14.0\GSPlayer.exe" -dpclient.

A Client process requires approximately 6Mb of memory when it is loaded prior to being accessed by the Controller process. Hence, for most machines, the act of loading the Client process will not significantly impact anyone who is using that particular machine. Moreover, once a Controller process accesses the Client (and begins to send it realizations to process), the priority of the Client is lower than that of other processes running on the machine. As a result, although an active Client will slow the system down somewhat, the machine can still be used for other applications, with the GoldSim Client process running in the background.

Note: You can run multiple Client processes on a multi-core or multi-processor computer to increase performance. For a multi-processor computer, the recommended number of GoldSim processes (Controller and Client) is equal to the number of processors. For a multi-core computer, the recommended number of GoldSim processes (Controller and Client) is equal to the total number of cores minus one. You must launch each process separately (such that each process is present in the Windows Task Bar).

If you launch a Client process from the command line, the following dialog will be displayed on the Client machine:

差 GoldSim DP Client #1 : Port 5563		×
Status: Client is ready to connect to Controller.		
Realization:		0:00:00
Critical Events:		

Pressing the X in the upper right-hand corner will terminate the Client process (close the GoldSim Client executable) so that it can no longer be accessed by a Controller process. A Client can also be terminated remotely by the Controller process.

Read More: Terminating Clients from the Controller Process on page 17

Configuring Windows Firewall to Permit Connections to Client Processes

If a machine has the Windows Firewall enabled, GoldSim or the GoldSim Player must be added to the Windows Firewall's Exception List in order to manually start Client Processes.

The first time that GoldSim or the GoldSim Player is started as a Client process manually, the Windows Firewall will ask if you wish to unblock the program.

In Windows 10 you will see the following:



For security purposes, you should ensure that only the Domain Networks option is checked. Then click the **Allow Access** button.

If you were not prompted to unblock the program, it may already have been added to the Windows Firewall Exception List.

You can check that the program has been correctly added by opening the Control Panel, clicking on Windows Firewall and then clicking (in the upper left) "Allow an app or feature through Windows Firewall".

📸 Allowed apps			- 1		×
← → × ↑ 🔐 « Windows Firewall > Allowed apps 🗸 🗸	Search	h Control I	Panel		Q
Allow apps to communicate through Windows Firewall To add, change, or remove allowed apps and ports, click Change settings. What are the risks of allowing an app to communicate? Allowed apps and features:		€ Ch	ange setti	ings	
Name	Domain	Private	Public	^	
GlassWire Service					
GoldSim Player					
GoldSim Pro					
GoldSim vendor daemon for Flexera Imadmin license server.	✓				
GoldSim vendor daemon for Flexera Imadmin license server.					
🗹 goldsim.exe					
Google Chrome		✓	✓		
Groove Music	\checkmark	✓	✓		
✓ HomeGroup		✓			
☑ Hyper-V		✓	✓		
Hyper-V Management Clients	✓	✓		\checkmark	
	Deta	iils	Remove	2	
		Allow an	other app)	
		ОК	Cano	el	

GoldSim or the GoldSim Player will be listed. If the box to the left is checked, the program is already unblocked. If it is unchecked, simply check the box to unblock the program.

You can check that the program has been correctly added by clicking the Start button on the Desktop and then typing Windows Firewall into the Search field. Select "Windows Firewall with Advanced Security" from the Search results (note, to get this to appear in the search results, it may be necessary to type more than Windows Firewall). When the program opens, select Inbound Rules on the left-hand side. You'll see the following dialog:

📸 Windows Firewall with Advance	ed Security							×	
File Action View Help									
🗢 🄿 🙍 🖬 🔒 🛛 🗊									
Pindows Firewall with Advance	Inbound Rules				Act	tions			_
K Inbound Rules	Name	Group	Profile	Enabl ^	Inb	ound Rules			^
Connection Security Rules	🥑 GoldSim Player		Domain	Yes	13	New Rule			
> 🔜 Monitoring	🚱 GoldSim Pro		Domain	Yes		Filter by Pro	ofile	•	
	🔮 GoldSim Pro		Domain	Yes		E11 1 01			
	🧭 GoldSim vendor daemon for Flexera Ima		Domain	Yes	Ψ.	Filter by Sta	te	•	
	🛇 GoldSim vendor daemon for Flexera Ima		Public	Yes	7	Filter by Gro	oup	►	
	GoldSim vendor daemon for Flexera Ima		Domain	Yes 💙		View		Þ	
< >>	<			>					~

GoldSim and/or the GoldSim Player should show Yes under the Enabled column. If they are not enabled, double click the entry and check the Enabled box on the General tab of the dialog that appears:

GoldSim Pro F	Propertie	25				×
Protocols and General	l Ports	Scope Program	Advanced s and Services	Local Prin	icipals Remote (Remote Users Computers
General N D	ame: àoldSim F escriptior àoldSim F	Pro n: Pro				
Action	 Enable Allow t Allow t 	ed he connec he connec	tion tion if it is secur	e		× .
C	Cust	omize the connec	ction			
			ОК	С	ancel	Apply

Connecting the Controller Process to the Clients

To start a distributed processing simulation from a Controller process, start GoldSim, load the model file which you wish to run, and select **Run** | **Run on Network...** from the main menu. The following dialog will be displayed:

Distributed	Processing Control	ler		—		×
Status: Progress:	Ready for client con	nections				
#	Client Address	Active	Status			Ţ
						R
						P
						e.
						† ↓†
Critical Eve	nts:					
					Rur	n
					Abo	rt
					Clos	e

Note: The option to **Run** | **Run on Network...**is only available if multiple realizations have been specified. That is, a distributed processing simulation cannot be carried out on a single realization.

The next step is to specify the names of the machines that will host the Client processes.

Note: The list of computer addresses for Client processes is saved to the Registry when you close the DP Controller dialog, so that the addresses you used the last time you ran a distributed processing run will be available the next time the Run on Network dialog is opened.

Note: You can assign up to 32 Clients to one computer. The DP clients use ports 5563 through 5594.

If multiple Client processes will be run on a single PC, the name of that PC should appear as many times as the desired number of Client processes. You can add machine names manually, or by importing a list of Clients that you have previously entered and saved.

Read More: Importing and Exporting Client Lists on page 16

To add Clients, press the Add client button:



This will display the following dialog:

New DP Client Address		×
Enter Client address		OK
Address:	Browse	Cancel
Instances: 1		Help

You can use the **Browse...** button to find a computer on your network, or you can enter a network ID or IP address directly. The **Instances** control allows you to create multiple instances of the same computer/address (in order to use multiple processors on that machine). This number must be between 1 and 32, inclusive.

Note: If a Client Process is to be run on the local machine, you can simply type *localhost* for the computer name. If you are running multiple Clients on your computer (i.e., using multiple processors) you should specify *localhost* as the client (e.g., if you wanted to use two local processors, you would specify *localhost* as the **Address** and set **Instances** to 2).

When you add a Client (and specify the **Instances**) and press the **OK** button, the Client is added to the list. In this example, two local processors have been specified:

ischo	uted Processing Contro	ller			×
Status Progre	: Ready for client cor	nnections			
#	Client Address	Active	Status		
1	localhost				-
2	localhost			 	_ <u>×</u> _
					Ŗ
					B
					a
					C
ritical	Events:				.:
Critical	Events:			Ru	
Critical	Events:			Rur Abo	€
Critical	Events:			Rur Abo	€ ÷÷ †↓† n rt

After adding Clients you can activate them by pressing the **Update clients** button:



The Controller process then does the following:

- 1. Finds the specified computers on the network;
- 2. Checks to see if a GoldSim Client process is running and available on the computers.

GoldSim then reports the status of the Clients in the dialog:

Distrik	outed Processing Controll	er		-		×
Status Progre	s: ess:					
#	Client Address	Active	Status			
1	localhost	\checkmark	DP Client is running and ready (5563)			
2	localhost		DP Client is running and ready (5564)			_ <u>×</u> _
						R
						B
						8
						\otimes
						† ↓†
Critica	al Events:					
Conn	ection to localhost establish	ed on Por	t 5563		Ru	In
Conn	lection to localnost establishe	ed on Por	1 2204		Abo	ort
					He	lp
					Clo	se

Note: Unless you have licensed the Distributed Processing Plus (DP Plus) module, you will be limited to using four Client processes at a time. If you have listed more than four Client processes, when you press the **Update clients** button, GoldSim will only activate four, and the other Client processes will be inactive.

The dialog for Client processes indicates when a connection with a Controller process has been made (and that it is waiting for a request):

着 GoldSim DP Client #1 : Port 5563 — 🛛							
Status: Waiting for a r	equest from Controller.						
Realization:				0:00:00			
Critical Events:							

You can subsequently remove Client process entries from the list in the Controller dialog by selecting an address and pressing the **Remove client** button:



If necessary, existing addresses in the Client process list can also be edited directly.

Importing and Exporting Client Lists

The list of Client computer addresses is saved to the Registry when you close the Distributed Processing Controller dialog, so that the addresses you used the last time you ran a distributed processing run will be available again the next time you wish to carry out a distributed processing run (and you will not have to reenter them).

In some cases, however, you may use different sets of Clients for different runs, or you may want to copy a list of Clients from one computer to another. To facilitate this, GoldSim allows you to export and import lists of Clients using the **Import client list** and **Export client list** buttons:



Once you have entered a list of Clients, pressing the **Export client list** button prompts you to specify a filename for the list of Clients. The file has a .DPL extension. You can subsequently import this list of Clients by pressing the **Import client list** button and specifying a .DPL filename. When you do so, GoldSim will ask if you want to remove any existing Client processes that are already in the dialog and will ask if you want to update the status of all Client processes immediately.

Terminating Clients from the Controller Process

You can terminate (close) a Client process from the machine on which the Client is running so that it can no longer be accessed by the Controller.

Read More: Running GoldSim in Client Mode on page 8

You can also terminate Clients from the Controller machine. To terminate all Clients, press the **Terminate all clients** button:



This is typically what you would do when you complete your simulation. You can terminate an individual Client process by clearing the **Active** checkbox. When you do this, you will be presented with a dialog asking if you want to terminate the Client process or simply make it inactive (i.e., stop using it, but keep it open).

Read More: Activating, Deactivating and Terminating Client Processes During a Simulation on page 21

Warning: Although the Controller process can terminate Client processes, it cannot launch them. A Client process can only be restarted by opening the process locally on the remote machine.

Updating the Status of Client Processes

In some situations, the status of a Client could change in such a manner that the Controller process would not be aware of the change (until it tried to send realizations to the Client). This could happen, for example, if a Client machine was turned off, or if it was rebooted prior to the beginning of the simulation.

The **Update clients** button provides a mechanism by which the Controller process can recheck the status of the Clients prior to starting a simulation (in case some action needs to be taken, for example, if one of the Client machines has been disabled):



Pressing the Update clients button updates the status of all Clients.

Running a Distributed Processing Simulation

Once you have connected to at least one Client process, you can run a simulation. To do so, press the **Run** button in the Distributed Processing Controller dialog.

During the simulation, the Distributed Processing Controller dialog will display the status of each Client process:

Distrib	uted Processing Controll	er			×
Status	: Simulation is running.				
Progre	ss:				
#	Client Address	Active	Status		
1	localhost	\checkmark	DP Client is running and ready (5563)		-0-
2	localhost		DP Client is running and ready (5564)		
					민
					P
					$\cdot e_{i}^{(a)}$
					ţţţ
Critical	Events:				
Conne	ection to localhost establish	ed on Por	t 5563	Ru	ın
Initial	ize network kun			Ab	ort
				He	lp
				Clo	se

The overall status of the simulation (based on the fraction of realizations that have been completed) is displayed at the top of the dialog. The status of each Client process (i.e., the realization currently being processed) is displayed under Status.

Note: When running a distributed processing simulation, the GoldSim Run Control Toolbar and Status bar are not used. The progress of the simulation is monitored from the Distributed Processing Controller dialog rather than the main application status bar.

When a distributed processing simulation is started, the Controller process first transfers the model file (and any other required files) to each of the Client processes.

Read More: Distributed Processing Auxiliary Files and Working Folders on page 22

Once the Client processes have received the required files, they can begin to receive and process realizations. The Controller process assigns and sends individual realizations to each Client process, which then carries out its assigned realization, and then sends the results to the Controller process. The Client process is then assigned a new realization by the Controller process. This continues until the specified number of realizations have been run.

On machines with active Client processes, the Client dialog indicates the current status of the Client:

🔂 GoldSim DP Client #1 : Port 5563	_	×
Status: Running simulation		
Realization: 108		0:00:02
Critical Events:		

Once all of the realizations have been completed, the Controller process combines all of the results into a single GoldSim file (and displays a "Simulation Complete" dialog) just as if the entire simulation had been carried out on the Controller process's machine:

Simulation Complete X
There were 0 warnings and no fatal errors. View Run Log
100 of 100 realizations
Total Simulation Time: 0:02:21
The results have been saved to the current file. If you wish to, you can archive these results. Archiving allows you to save the results to another file, and return to the current file.
Close Archive Help

When you close the Simulation Complete dialog, the Distributed Processing Controller dialog is still open, and looks like this:

Distributed Processing Controller — 🗆 🗙							
Status: Exiting DP Controller Run Thread							
Progre	SS:						
#	Client Address	Active	Status				
1	localhost	\checkmark	DP Client is ready				
2	localhost		DP Client is ready	_ <u>*</u> _			
				R			
				P			
				ela.			
				\otimes			
				† ↓†			
Critical	Events:						
Conne	ection to localhost establishe	d on Por	t 5563	un			
Abort							
			H	elp			
			Q	ose			

To browse the GoldSim model and view the results, press the Close button.

Assigning Multiple Realizations to Each Client Transaction

When modeling systems with low-probability, high-consequence outcomes it is sometimes necessary to run a large number of realizations. When a realization can be run quickly the amount of time spent transferring information to Client processes for each realization individually can negate the performance benefits of distributed processing. As a result, GoldSim has an option to assign a block of realizations to a Client process. This option is accessed by pressing the **Additional Client Settings** button:

10	×
E	
-	
	Ţ
2	
}	R
) -	B
j.	8
í.	\otimes
5	†↓†

When you do so, the following dialog is displayed:

Advanced Distributed Processing Settings					
Client Simulation Parameters Realizations to run per client transaction: 1 -	OK Cancel Help				

A block of realizations can be assigned to a Client process by using the **Realizations to run per client transaction**.

By default the value is 1 (indicating a single realization will be assigned each time). The value can be increased to any number that is desired (e.g. specifying 5 means that the first Client transaction will assign realizations 1-5, the second 6-10 and so on).

Aborting a Distributed Processing Simulation

While a distributed processing simulation is running, you may choose to abort the simulation before it is complete (i.e., in order to select a new group of computers to host Client processes). You can do this by pressing the **Abort** button in the Distributed Processing Controller dialog.

When the simulation is aborted, The Simulation Complete dialog is displayed. Completed realizations are retained. All Client processes will be deactivated (but left running). When you close the Simulation Complete dialog, the Distributed Processing Controller dialog is displayed and all options are fully editable. When you close this dialog, if you subsequently press the **Update clients** button (to reactivate the Clients), the **Run** button is activated and is renamed **Run/Resume**.

If the Run/Resume button is pressed, GoldSim displays this dialog:

Distributed Processing X						
The previous run of this simulation was not completed. Do you want to resume the previous run at the point when it was halted, or start a new run from the beginning?						
Resume Run		Start New Run	Cancel	Help		

There are three buttons (in addition to Help):

Resume Run. This option makes use of realizations completed prior to the simulation being aborted, and runs the remaining realizations using the current list of Client processes.

Start New Run. This option discards all completed realizations and re-runs the entire simulation.

Cancel. Returns to the Controller dialog.

If the **Close** button is pressed in the Distributed Processing Controller dialog, GoldSim assembles completed realizations up to the first gap in the realization sequence, and places the model into Result Mode. For example, if realizations 1,2,3,4, 6 and 7 were completed, only realizations 1,2,3, and 4 would be assembled and available in Result Mode.

Activating, Deactivating and Terminating Client Processes During a Simulation

Once you have started a distributed processing simulation, you can choose to activate an inactive Client process (e.g., if a machine becomes available) or deactivate a Client process that is currently active (e.g., if a user requires the machine for other work, or the machine's performance is not sufficient).

You activate an inactive Client process by simply clicking on the **Active** checkbox. The Controller process will automatically try to connect to the Client, and if successful, will begin to send it realizations.

Read More: Connecting the Controller Process to the Clients on page 12

You can deactivate or terminate an active Client process by clearing the **Active** checkbox. The Controller process will redirect the realization that the Client process was working on to another Client process, and will send no additional realizations to the Client process (unless it is subsequently reactivated).

Similarly, if a Client process is terminated during a simulation (i.e., if the Client process is closed, or if the machine hosting the process is turned off or rebooted), the Controller process will redirect the realization that that Client process was working on to another Client process, and will send no additional realizations to the terminated process.

Note: If an active Client process is terminated (by first deactivating the Client in the Distributed Processing Controller dialog and then closing the Client dialog or turning off the Client machine) and then restarted during a simulation, the Controller process will not automatically reconnect to the Client process and start to use it again. To reestablish the connection, you must check the **Active** checkbox for that Client process in the Distributed Processing Controller dialog.

Distributed Processing Auxiliary Files and Working Folders

When a distributed processing simulation is started, the first thing that the Controller process does is to transfer the model file (and any other required files, such as spreadsheets referenced by Spreadsheet elements, DLLs referenced by External elements, and all File elements) to each of the Client processes.

The files are copied to a working folder on the machine hosting the Client process. The location of the working folder varies depending on the operating system. The best way to access the folder is to use variables provided by the operating system. Enter the following directly into the address bar for Windows Explorer:

%ALLUSERSPROFILE%\GTG

Within this folder will be a working folder called "DPClient*iiii*", where *iiii* is the port number. (If you run multiple Client processes on a single system, each port will have it own working folder). An index file (index.gst) is generated by GoldSim inside each working folder. This file stores information about any auxiliary files that have been saved in the folder.

Note: This is the default location for the folder. You can manually change this by editing the registry and creating a key called GoldSimDataFolder with the folder location under HKEY_CURRENT_USER\Software\GTG\GoldSim\DistributedProcessing.

If the GoldSim model uses External elements or External Pathway elements, copies of their DLL files will be created in the Client's local working folder.

If the GoldSim model uses Spreadsheet elements, then:

- If the associated spreadsheet file has a full pathname (e.g., "C:\test\file.xlsx") then it will be copied to the same path on the Client system under the working folder created by GoldSim (e.g., DPClientiiii\test\file.xlsx).
- If the associated spreadsheet file has a local pathname (e.g., "testfile.xlsx) then it will be copied into the Client's working folder.
- If the associated spreadsheet file has a relative pathname (e.g.,".\xyz\testfile.xlsx") then it will be copied to a path on the Client system under the working folder created by GoldSim (e.g., DPClientiiii\xyz\test\file.xlsx).

Warning: When doing distributed processing simulations, any referenced files (e.g., spreadsheets and DLLs) must be stored in the same folder as the GoldSim model file (or subfolders within that same folder). Relative paths to folders outside of the model folder should not be used.

If you use a File element, the same rules discussed above for spreadsheet files apply to the File Element's local file name.

You can control whether or not the files in the working folders are saved at the end of the simulation. This option is accessed by pressing the **Additional Client Settings** button:



When you do so, the following dialog is displayed:



Files to keep on Client after simulation has three options:

None: All files generated by the Client process (as well as the working folder itself) are deleted.

Auxiliary Files (default): Any auxiliary files transferred to the Client process (e.g., DLLs, spreadsheets) are saved, but any intermediate files that might have been generated independently by the Client process (e.g., via DLLs) are not saved.

All Files: Any auxiliary files transferred to the Client process (e.g., DLLs, spreadsheets) are saved, *and* any intermediate files that might have been generated independently by the Client process (e.g., via DLLs) are also saved.

Note: The gsm file itself is never saved in the working folder.

Note: If a Client machine is turned off during a simulation, its working folders are not deleted.

While a distributed processing simulation is running, results sent back to the Controller process are stored in temporary result files in the same directory as the model file. One file is created for each realization (or set of realizations), and named ModelFilename-RealX.gsr, where ModelFilename is the name of the model file, and X is the realization number (if a set of multiple realizations are saved, the filename becomes ModelFilename-RealX-Y.gsr, where X is the first realization in the set and Y is the last realization in the set). By default, these files are deleted when the Controller process assembles all of the results into the model file.

Note: In some cases it is necessary to retain the temporary results files (e.g., to allow for recovery if the Controller process crashes). GoldSim provides a mechanism to do this by modifying a registry setting.

Read More: Recovering a Simulation When the Controller Process Fails on page 24

Assigning Realizations to Multiple Clients at the End of the Simulation

In some cases, when running a simulation with multiple realizations, it is possible that one or more of the realizations may "stall" or run very slowly for unanticipated reasons (e.g., due to hardware issues on the Client machine, or just because that particular Client is slow). In this situation, it is possible for all of the realizations except a small number to be complete. As a result, the simulation may take an extremely long time to finish (as it is waiting for the last few realizations to complete on the "slow" Clients).

To address this situation, toward the end of a simulation, if one or more Clients have no realizations assigned to them, you can instruct GoldSim to assign any incomplete realizations to the unused Clients. As a result, a realization can be assigned to multiple Clients. As soon as one of the Clients completes the realization, the other Clients working on the same realization are told to stop.

You can enable this behavior so that unfinished realizations are assigned to idle Clients by creating a registry DWORD called EnableReassignRealization in HKEY_CURRENT_USER\Software\GTG\GoldSim\Settings\ and setting it equal to a nonzero value. A value of 0 (or absence of the key) disables the behavior.

Note: This key is only meaningful if defined on the computer running the Controller process.

Recovering a Simulation When the Controller Process Fails

Occasionally there will be situations where the computer hosting the Controller process crashes. If temporary result files are retained on the computer completed realizations can be recovered.

By default the temporary result files are processed (and deleted) as the simulation is running (to conserve disk space). To retain these files until the completion of the simulation, create a DWORD called DelayDeleteGSR in HKEY_CURRENT_USER\Software\GTG\GoldSim\Settings\ and set it equal to a value of 1.

When GoldSim is restarted and the model file that was being worked on is reopened, GoldSim will search for these temporary files when the **Run**|**Run on Network** option is selected. The following dialog will be displayed:



Pressing **Yes** will allow use of the completed realizations from the run where the Controller process crashed. When you enter the Distributed Processing Controller dialog the **Run** button will be labeled **Run/Resume**. Clicking the **Run/Resume** button and then the **Resume Previous Run** option will run the remaining realizations needed to complete the simulation.

Pressing No will erase the temporary files from the interrupted run.

Distributed Processing Log Files

When carrying out a distributed processing simulation, GoldSim creates ASCII log files for the Client processes. Each Client process has a log file named "DPClientLog*iiii*.log", where *iiii* is the port number used by the Client. This file is located one level up from the Client's working folder (typically, C:\ProgramData\GTG).

Log files document the communication that takes place between the Controller process and Client processes, and can be useful for debugging purposes.

Limitations of the Distributed Processing Module

For the most part, if you need to run Monte Carlo simulations for a complex model, the use of the Distributed Processing Module is advantageous and strongly encouraged. There are some situations, however, in which use of the Distributed Processing Module may not be feasible.

In particular, because a distributed processing simulation requires that potentially large quantities of data (i.e., the GoldSim model file and other associated files, the results of each realization) be passed between the Controller process and Client processes over a network, effective use of the Distributed Processing Module requires fast network connections (and fast computers). If the connections between the processes are slow, a distributed processing simulation may be impractical.

In addition, there are three situations in which distributed processing is not supported at all:

- You cannot run multiple scenarios (using the Scenario Manager) and utilize distributed processing. That is, the Scenario Manager provides no access to distributing processing capabilities.
- Because distributed processing can not be used for a single realization, and high resolution results (in which all unscheduled timesteps are displayed) are only available for single realizations runs, high resolution results (i.e., time histories that include unscheduled updates) can never be viewed for distributed processing simulations.
- You cannot export results to a Spreadsheet element when doing a distributed processing run (as each realization would result in a different spreadsheet file).

Scenarios, high resolution results and Spreadsheet elements are discussed in detail in Chapters 7, 8 and 10, respectively of the <u>GoldSim User's Guide</u>.

Glossary

С

Client

Also referred to as a Client process. A GoldSim executable running on a client machine that can be used to carry out distributed processing of a Monte Carlo simulation using the Distributed Processing Module.

Controller Process

A GoldSim executable that manages Client processes in order to carry out distributed processing of a Monte Carlo simulation using the Distributed Processing Module.

D

DP Plus

A premium version of the Distributed Processing Module that allows an unlimited number of Client processes to be used.

Index

A

Aborting a distributed processing simulation 21 Activating Clients 21 Adding Clients for distributed processing 12

В

Blog 4

С

Client closing 8 configuring firewall 10 connecting to 12 importing and exporting 16 running GoldSim as a 8 terminating 8 terminating remotely 17 updating status 17 Client process defined 8 Closing Clients 8 Clients remotely 17 Connecting to GoldSim Clients 12 Controller process defined 8

D

Deactivating Clients 21 Distributed processing aborting a simulation 21 activating/deactivating Clients 21 assigning multiple realizations 20 auxiliary files 22 closing a Client 8 connecting to Clients 12 importing/exporting Clients 16 limitations 25 log files 25 overview 8 recovering simulation after failure 24 running a simulation 18 starting a Client 8 terminating Clients remotely 17 updating Client status 17 Distributed Processing Module description 2 overview 8 steps for using 8 versions 2 DP Plus 2

Ε

Exporting Client lists 16

F

Files used by Clients 22

G

GoldSim running in Client mode 8

Η

Help system 3

Importing Client lists 16

Μ

Maintenance program 4 Model Library 4

R

Realizations per Client transaction 20 Running a model distributed processing simulation 18

S

Support 4

Т

Technical support 4 Terminating Clients 8 Clients remotely 17 Training 4

U

Updating, Client status 17